



Proxmox VE 8: Advanced Administration and Optimization

Installation and Configuration Guide

Document Version: 2025-05-05

Contents


1	Introduction	3
1.1	Introducing the Proxmox VE 8: Advanced Administration and Optimization Pod 3	
2	Planning.....	4
2.1	Pod Creation Workflow.....	4
2.2	Pod Resource Requirements.....	5
2.3	ESXi Host Server Requirements	5
2.4	NETLAB+ Requirements	5
2.5	NETLAB+ Virtual Machine Infrastructure Setup	6
2.6	Software Requirements	6
2.7	Networking Requirements.....	6
3	Software and Licenses	7
3.1	Downloading OVF Files	7
3.1.1	Virtual Machine Credentials	7
4	Master Pod Configuration.....	8
4.1	Deploying Virtual Machine OVF/OVA Files	8
4.1.1	Modify Virtual Machines.....	9
4.2	NETLAB+ Virtual Machine Inventory Setup	12
4.3	Building the Master Proxmox VE 8: Advanced Administration and Optimization Pod 13	
4.3.1	Enabling Labs in Course Manager	13
4.3.2	Create the Master Pod.....	13
4.3.3	Attach Virtual Machines to the Master Pod	15
4.3.4	Create Snapshots for the Master Virtual Machines	16
4.3.5	Set the Revert to Snapshot	19
5	Pod Cloning	21
5.1	Linked Clones and Full Clones.....	21
5.2	Creating User Pods.....	21
5.3	Copying Your Master Pod to the Second Host	23
5.4	Creating User Pods on the Second Host	25
5.5	Assigning Pods to Students, Teams, or Classes	25

1 Introduction

This document provides detailed guidance on performing the installation and configuration of the *Proxmox VE 8: Advanced Administration and Optimization* pod on the *NETLAB+ VE* system.

1.1 Introducing the Proxmox VE 8: Advanced Administration and Optimization Pod

The *Proxmox VE 8: Advanced Administration and Optimization* pod is a 100% virtual machine pod consisting of seven virtual machines. Linked together through virtual networking, these five virtual machines provide the environment for a student or a team to perform the *Proxmox VE 8: Advanced Administration and Optimization* labs.



Proxmox® is a registered trademark of Proxmox Server Solutions GmbH.

2 Planning

This guide provides specific information pertinent to delivering the *Proxmox VE 8: Advanced Administration and Optimization* pod. The [NETLAB+ Remote PC Guide Series](#) provides the prerequisite guidance for setting up your VMware infrastructure, including:

- An introduction to virtualization using *NETLAB+*
- Detailed setup instructions for standing up *VMware vCenter* and *VMware ESXi*
- Virtual machine and virtual pod management concepts using *NETLAB+*

This document assumes that you have set up virtual machine infrastructure in accordance with the [NETLAB+ Remote PC Guide Series](#). The planning information below refers to specific sections in the *Remote PC Guide* when applicable.

2.1 Pod Creation Workflow

The following list is an overview of the pod setup process.

1. Obtain the master virtual machine images required for the master pod.
2. Deploy the master virtual machine images to your *VMware vCenter Appliance*.
 - a. Deploy virtual machines using **Thin Provisioning** to reduce storage consumption.
 - b. Make necessary adjustments to each virtual machine in the environment.
 - i. Insert/Verify manual **MAC** addresses.
 - ii. Change the default network to **SAFETY NET**.
 - iii. Any other configuration changes mentioned in this guide.
3. Import the deployed virtual machines to the *NETLAB+ Virtual Machine Inventory*.
4. Activate or license the required software on each virtual machine when prompted.
5. Take a snapshot of each virtual machine in the master pod labeled **GOLDEN_MASTER** after all configurations and licensing have taken effect. The *GOLDEN_MASTER* snapshot is used to clone virtual machine images for the user pods.
6. Use the *NETLAB+ Pod Cloning* feature to create student pods from the master pod.
7. If multiple hosts are used in the *NETLAB+* environment, make a **Full Clone** of the master pod on the initial host (Host A) to the subsequent host (Host B) and so on using the *NETLAB+ Pod Cloning* feature.

2.2 Pod Resource Requirements

The *Proxmox VE 8: Advanced Administration and Optimization* course will consume 127.8 GB of storage per each master pod instance.

The following table provides details of the storage requirements for each of the virtual machines in the pod.

Virtual Machine	OVF/OVA	Initial Master Pod (Thin Provisioned)	Maximum Allocated Memory
Client	7.5 GB	16.3 GB	2 GB
NAS	73.9 GB	86.9 GB	4 GB
Server1	16.1 GB	25.4 GB	8 GB
Server2	15.9 GB	25.0 GB	4 GB
Server3	14.4 GB	22.4 GB	4 GB
Total	127.8 GB	176.0 GB	22.0 GB

2.3 ESXi Host Server Requirements

Please refer to the *NDG* website for specific *ESXi* host requirements to support virtual machine delivery: <https://www.netdevgroup.com/products/requirements/>

The deployment of the *Proxmox VE 8: Advanced Administration and Optimization* pod requires VMware ESXi version of **6.0** or greater.

**Please
Note**

The number of **active** pods that can be used simultaneously depends on the *NETLAB+* product license and the number of *VMware ESXi* host servers meeting the hardware requirements specifications.

For current *ESXi* server requirements and active pod count, refer to the following URL:

http://www.netdevgroup.com/support/remote_pc.html#vm_host_server_specifications.

2.4 NETLAB+ Requirements

Installation of *Proxmox VE 8: Advanced Administration and Optimization* pods, as described in this guide, requires that you are running *NETLAB+ VE 22.8.7* at a minimum.

Previous versions of *NETLAB+* do not support the requirements for the *Proxmox VE 8: Advanced Administration and Optimization* course on the physical host servers.

Please refer to the [NETLAB+ Remote PC Guide Series](#).

2.5 NETLAB+ Virtual Machine Infrastructure Setup

The *NETLAB+ Virtual Machine Infrastructure* setup is described in the following sections of the [NETLAB+ Remote PC Guide Series](#):

- *Registering a Virtual Datacenter in NETLAB+*
- *Adding ESXi hosts in NETLAB+*
- *Proactive Resource Awareness*



It is important to configure *Proactive Resource Awareness* to maximize the number of active pods per physical ESXi host.

2.6 Software Requirements

For the purpose of software licensing, each virtual machine is treated as an individual machine, PC, or server. Please refer to the specific vendor license agreements (and educational discount programs, if applicable) to determine licensing requirements for your virtual machines' software, operating system, and applications.

The minimum virtual infrastructure software required for standing up this pod is in the following table.

Virtual Infrastructure Requirements	
Software	Version
vSphere ESXi	6.0
vCenter Server	6.0

Please refer to the *Software and Licenses* section regarding the software requirements for virtual machines in the pod.

2.7 Networking Requirements

To accommodate the movement of large VMs, OVF/OVAs, and ISO disk images from one host to another, gigabit Ethernet or better connectivity is recommended to interconnect your NETLAB+, vCenter Server system, and ESXi host systems.

The two standard networking models recommended to interconnect your servers are described in detail in the *Networking Models* section of the [Remote PC Guide Series, Volume 1 - Introduction and Planning](#).

3 Software and Licenses

3.1 Downloading OVF Files

The virtual machines are made available as *Open Virtualization Format (OVF)* or *Open Virtualization Archive (OVA)* files. These files are available for download from *EPNC (Education Pathway National Center)*.

To request access to the preconfigured virtual machine templates from *EPNC*:

1. Go to the *CSSIA Resources* page: <https://www.caeepnc.org/cssiaresources/>
2. Select **CSSIA VM Image Sharing Agreement**.
3. Complete and submit your access request by following the instructions on the request form.
4. *EPNC* will provide, via email, password-protected download links. Access to the download links is provided only to customers who are current with their NETLAB+ support contract and are participants in the appropriate partner programs (*i.e., Cisco Networking Academy, VMware IT Academy, Red Hat Academy, and/or Palo Alto Networks*).
5. Once all virtual machines have been downloaded, they can be deployed following the steps in the appropriate pod installation guide. Each virtual machine is deployed individually.

3.1.1 Virtual Machine Credentials

For your reference, the following table provides a list of the credentials for the systems in the pod:

Machine	User name	Password
Client	administrator	NDGlabpass123!
NAS	root	NDGlabpass123!
Server1	root	NDGlabpass123!
Server2	root	NDGlabpass123!
Server3	root	NDGlabpass123!

4 Master Pod Configuration

4.1 Deploying Virtual Machine OVF/OVA Files

Deploy on your host server the pod virtual machine *OVF/OVA* files you have downloaded.

1. Navigate to your **vSphere Client** using your management workstation, ensure that your downloaded *OVA/OVF* files are accessible on this machine, and then connect to your **vCenter Server**.
2. From the *vSphere Client* interface, navigate to **Hosts and Clusters**.
3. Right-click on the target **ESXi Host Server** and select **Deploy OVF Template**.
4. In the *Deploy OVF Template* window, on the *Select source* step, select the **Local File** radio button and click **Browse**.
5. Locate and select one of the VMs for the pod, click **Open**.

VM Name	VM OS	Virtual Machine OVA Name
Client	Ubuntu	PVE8_AAO_FM.Client
NAS	TruesNAS Core	PVE8_AAO_FM.NAS
Server1	Proxmox VE 8	PVE8_AAO_FM.Server1
Server2	Proxmox VE 8	PVE8_AAO_FM.Server2
Server3	Proxmox VE 8	PVE8_AAO_FM.Server3

Please Note

Only one VM can be selected using this wizard. The process will have to be repeated for the remaining VMs.

6. Verify that the VM information populates next to the *Browse* button and click **Next**.
7. On the *Review details* step, make sure to fill the checkbox for **Accept extra configuration options (if present)** and click **Next**.
8. On the *Select name and folder* step, change the name of the virtual machine to something that is easy to manage. You can use the names provided in the list below as names for the virtual machines if you do not have a set naming convention. Select the appropriate **datacenter** and click **Next**.

VM Name	VM OS	Virtual Machine Deployment Name
Client	Ubuntu	PVE8_AAO_Master.Client
NAS	TruesNAS Core	PVE8_AAO_Master.NAS
Server1	Proxmox VE 8	PVE8_AAO_Master.Server1
Server2	Proxmox VE 8	PVE8_AAO_Master.Server2
Server3	Proxmox VE 8	PVE8_AAO_Master.Server3

9. On the *Select Storage* step, choose the appropriate storage device and make sure that **Thin Provision** is selected. Click **Next**.

10. In the *Setup networks* section, select **SAFETY NET** as the destination and click **Next**.



If **SAFETY NET** is not available, refer to the *Create a Safe Staging Network* section in the [Remote PC Guide Series – Volume 2](#).

11. In the *Ready to complete* section, make sure **Power on after deployment** is **unchecked** and confirm the settings. Click **Finish**.
12. vCenter will begin deploying the virtual machine. This may take some time, depending on the speed of your connection, HDDs, etc. Repeat the previous steps for each remaining virtual machine in the master pod.

4.1.1 Modify Virtual Machines

Once the virtual machines are imported onto the host, verify the configurations. The following steps will guide you through the process.

1. In the *vSphere Client* interface, right-click on the imported virtual machine and select **Edit Settings**.
2. For all the virtual machines, manually assign the *MAC* addresses for each *NIC*. The table below identifies the *MAC* addresses per *NIC*.

Virtual Machine	NIC	MAC
Client	1	00:50:56:b3:02:c0
NAS	1	00:50:56:b3:e0:bc
	2	00:50:56:b3:b8:27
Server1	1	00:50:56:b3:21:f3
	2	00:50:56:b3:fa:92
	3	00:50:56:b3:20:cc
	4	00:50:56:b3:22:fb
Server2	1	00:50:56:b3:c7:b6
	2	00:50:56:b3:28:53
	3	00:50:56:b3:c4:a6
	4	00:50:56:b3:93:6c
Server3	1	00:50:56:b3:2a:ef
	2	00:50:56:b3:d7:d7
	3	00:50:56:b3:64:e3
	4	00:50:56:b3:8a:10



Edit Settings | PVE8_AAO_Master.Client



Virtual Hardware

VM Options

ADD NEW DEVICE ▾

> CPU	2 ▾	
> Memory	2 ▾ GB ▾	
> Hard disk 1	60  GB ▾	
> SCSI controller 0	VMware Paravirtual	
<input checked="" type="checkbox"/> Network adapter 1	SAFETY NET ▾	
Status	<input checked="" type="checkbox"/> Connect At Power On	
Adapter Type	VMXNET 3 ▾	
DirectPath I/O	<input checked="" type="checkbox"/> Enable	
MAC Address	00:50:56:b3:02:c0 Manual ▾	
> CD/DVD drive 1	Client Device ▾	<input type="checkbox"/> Connect...
> Video card	Specify custom settings ▾	
VMCI device		
> Other	Additional Hardware	

- While in the *Edit Settings* window, click on the **VM Options** tab and expand the **VMware Tools** section. **Check** the checkbox for **Synchronize guest time with host/Synchronize at startup and resume** to enable the feature. Click **OK** to save the configuration.

Edit Settings
PVE8_AAO_Master.Client

Virtual Hardware
VM Options

> General Options	VM Name: PVE8_AAO_Master.Client
VMware Remote Console Options <input checked="" type="checkbox"/>	Lock the guest operating system when the last remote user disconnects
> Encryption	Expand for encryption settings
> Power management	Expand for power management settings
VMware Tools	
Power Operations	<input type="button" value="▶"/> Power On / Resume VM <input type="checkbox"/> Shut Down Guest (Default) ▾ <input type="button" value="⏸"/> Suspend (Default) ▾ <input type="button" value="↺"/> Restart Guest (Default) ▾
Tools Upgrades	<input type="checkbox"/> Check and upgrade VMware Tools before each power on
Synchronize Time with Host ⓘ	<input checked="" type="checkbox"/> Synchronize at startup and resume (recommended) <input type="checkbox"/> Synchronize time periodically
Run VMware Tools Scripts	<input checked="" type="checkbox"/> After powering on <input checked="" type="checkbox"/> After resuming <input checked="" type="checkbox"/> Before suspending <input checked="" type="checkbox"/> Before shutting down guest
> Boot Options	Expand for boot options
> Advanced	Expand for advanced settings
> Fibre Channel NPIV	Expand for Fibre Channel NPIV settings

CANCEL
OK

- Repeat the previous steps for each of the remaining virtual machines in the master pod.

4.2 NETLAB+ Virtual Machine Inventory Setup

This section will guide you in adding your templates to the *Virtual Machine Inventory* of your *NETLAB+ VE* system.

1. Log in to your *NETLAB+ VE* system using the administrator account.
2. Select the **Virtual Machine Infrastructure** icon.




3. Click the **Virtual Machine Inventory** icon.




Virtual Machine Inventory

Import, clone, and manage the inventory of virtual machines to be used with NETLAB+.

4. Click the **Import Virtual Machines** button located at the bottom of the list.

 Import Virtual Machines

5. Select the appropriate datacenter from the list where your master VMs reside.
6. Select the checkbox next to the virtual machines you had just deployed and click **Import Selected Virtual Machines**.

 Import Selected Virtual Machines

7. When the *Configure VMs* window loads, you can set your virtual machine parameters.
 - a. Check the dropdown box for the correct operating system for each imported virtual machine.
 - b. Change *Role* to **Master** for each VM.
 - c. Add any comments for each virtual machine in the last column.



It is advised to leave the *Version* and *Build* numbers for reference when requesting *NDG* support.

- d. Verify your settings and click **Import (X) Virtual Machines** (notice the number in parenthesis is dynamic, depending on the amount of VMs selected).



- e. Verify all *Import Statuses* report back with *OK* and then click on the **Dismiss** button.
- f. Verify that your virtual machines show up in the inventory.

For additional information, please refer to the [NETLAB+ VE Administrator Guide](#).

4.3 Building the Master Proxmox VE 8: Advanced Administration and Optimization Pod

This section will assist you in adding the *Proxmox VE 8: Advanced Administration and Optimization* pod to your *NETLAB+* system.

4.3.1 Enabling Labs in Course Manager

Please refer to the *Course Manager* section of the [NETLAB+ VE Administrator Guide](#) on how to enable content. Please install the **Proxmox VE 8: Advanced Administration and Optimization – v8.0** course.




Proxmox VE 8: Advanced Administration and Optimization - v8.0

4.3.2 Create the Master Pod

1. Log into **NETLAB+ VE** with the *administrator* account.
2. Select the **Pods** icon.



3. Create a new pod by scrolling to the bottom and clicking the **Create New Pod** button.



- Then, click on the **Proxmox VE 8: Advanced Administration and Optimization** pod entry from the list of installed pod types.



- On the *New Pod* window, input a value into the **Pod ID** and **Pod Name** fields. Click **Next**.



The "New Pod" window shows the configuration for a new pod. The "Pod Type" is set to "Proxmox VE 8: Advanced Administration and Optimization". The "Pod ID" field contains the value "1000". The "Pod Name" field contains the value "PVE8_AAO_H120_M1000". A "Used Pod IDs" list on the right shows a range from 10 to 1025. At the bottom, there are "Next" and "Help" buttons.



The **Pod ID** determines the order in which the pods will appear in the scheduler. It is best practice to use a block of sequential ID numbers for the *Pod Id* that allows for the number of pods you are going to install.

The **Pod Name** identifies the pod and is unique per pod. Here we used the name of the lab set or course in a shortened form along with a host identifier (H120), the type and number of the pod (M1000).

- To finalize the wizard, click **OK**.

For additional information, please refer to the [NETLAB+ VE Administrator Guide](#).


4.3.3 Attach Virtual Machines to the Master Pod

Update the master pod to associate the virtual machines with the newly created pod.


1. Select the **Proxmox VE 8: Advanced Administration and Optimization** master pod from the pod list.



2. Click on the **Action** dropdown next to the virtual machine you are about to assign and select **Attach VM**.



3. Select the corresponding virtual machine from the inventory list.



4. Click **OK** to confirm the VM attachment and repeat the previous steps for the remaining virtual machines.

4.3.4 Create Snapshots for the Master Virtual Machines

In order to proceed with pod cloning, snapshots must be created on each of the pod's virtual machines.





Verify that all VMs are powered off before taking snapshots.

1. Make sure to view the **Proxmox VE 8: Advanced Administration and Optimization** master pod you just assigned machines to. In the pod view, click on the dropdown menu option underneath the *Action* column for a specific VM and select **Snapshots**.

Remote PC 5						
PC Name	VM	Operating System	VM Role	Runtime Host	Action	
 Client	PVE8_AAQ_Master.Client	Linux	MASTER		<div>  <ul style="list-style-type: none">  View  Settings  Attach VM  Remove VM From...  Snapshots </div>	
 Server1	PVE8_AAQ_Master.Server1	Linux	MASTER			
 Server2	PVE8_AAQ_Master.Server2	Linux	MASTER			
 Server3	PVE8_AAQ_Master.Server3	Linux	MASTER			
 NAS	PVE8_AAQ_Master.NAS	Free BSD	MASTER			






2. In the *Snapshot Manager* window, click on the **Take** button. This will take a snapshot of the current state of the virtual machine.


Snapshot Manager

Name:

Description:












Any changes made after this will require a new snapshot or those changes will not reflect in the reset state of the pod or its clones.

3. In the *Take Snapshot* window, type **GOLDEN_MASTER** into the *Name* text field, or you may choose another naming convention as long as it is consistent for easy management. Click **OK**.



Take Snapshot

Name:
GOLDEN_MASTER


Description:

OK Cancel



It is recommended to use *GOLDEN_MASTER* as the snapshot name when working with normalized pod types.

4. In the *Snapshot Manager* window, notice the snapshot is created. Click the **Dismiss** button.



At this point it is good to verify that you have only one snapshot on the virtual machine. Multiple snapshots increase the likelihood of having problems, especially if the snapshots are named the same. Also, the more snapshots a virtual machine has, the slower the performance and the more drive space is used.

5. Repeat the previous steps for the remaining virtual machines.

4.3.5 Set the Revert to Snapshot


1. Make sure to view the **Proxmox VE 8: Advanced Administration and Optimization** master pod you just created snapshots for. In the pod view, click on the dropdown menu option underneath the *Action* column and select **Settings**.

Remote PC 5						
PC Name	VM	Operating System	VM Role	Runtime Host	Action	
 Client	PVE8_AA0_Master.Client	Linux	MASTER			
 Server1	PVE8_AA0_Master.Server1	Linux	MASTER		<div>  View  Settings  Attach VM  Remove VM From...  Snapshots </div>	
 Server2	PVE8_AA0_Master.Server2	Linux	MASTER			
 Server3	PVE8_AA0_Master.Server3	Linux	MASTER			
 NAS	PVE8_AA0_Master.NAS	Free BSD	MASTER			

2. In the virtual machine's *Settings* window, click on the *Revert to Snapshot* dropdown and select **GOLDEN_MASTER** and then click the **Submit** button.



This sets the snapshot on the virtual machine that will get reverted to each time the pod is scheduled.

 **Client Settings**


PC Name

Client

PC Type

Virtual Machine

Datacenter



Virtual Machine

PVE8_AA0_Master.Client

Role

Master

Revert to Snapshot

GOLDEN_MASTER

Shutdown Preference


Graceful Shutdown


Guest Operating System


Linux

Options

☒ enable remote display auto-configuration
☒ enable network auto-configuration
☒ enable advanced setting auto-configuration
☒ enable minimum requirements verification

 **Submit**

 Cancel

 Help

3. Click **OK** to confirm.

4. Return to the pod view page and repeat the previous steps for the remaining virtual machines.

5 Pod Cloning

This section will help you create multiple student pods. The following sections describe the *NETLAB+* pod cloning feature used to create student pods on one or two host systems.

5.1 Linked Clones and Full Clones

NETLAB+ can create *linked clones* or *full clones*.

A **linked clone** (or linked virtual machine) is a virtual machine that shares virtual disks with the parent (or master) virtual machine in an ongoing manner. This conserves disk space and allows multiple virtual machines to use the same software installation. Linked clones can be created very quickly because most of the disk is shared with the parent VM.

A **full clone** is an independent copy of a virtual machine that shares nothing with the parent virtual machine after the cloning operation. The ongoing operation of a full clone is entirely separate from the parent virtual machine.

5.2 Creating User Pods

The following section describes how to create user pods on the same *VMware Host* system that holds your master pod's virtual machines. In this scenario, we will create linked virtual machines using the *NETLAB+* pod cloning utility.

1. Log in to **NETLAB+ VE** with the *administrator* account.
2. Select the **Pods** icon.



3. Click on your master pod.
4. Make sure the pod is offline by selecting **Take Pod Offline**.
5. Click the **Clone Pod** button to create a new pod, based on the settings and snapshots of this pod.



6. Input a new ID value into the **New Pod ID** field. It is advised to keep the pods in numerical order. If the pod IDs are not in numerical order, they will not show up in the scheduler in numerical order. Click **Next**.

7. Enter a name for the cloned pod into the **New Pod Name** field. For example, **PVE8_AAO_H120_S1001**. Click **Next**.



The **Pod Name** identifies the pod and is unique per pod. Here we used the name of the lab set or course in a shortened form along with a host identifier (H120), the type and number of the pod (S1001).


8. When the action has finished processing, you are presented with a settings screen. Notice each VM has its own tab. Go through each tab and verify the following:

Source Virtual Machine:

- a. *From Snapshot* should be set to the **GOLDEN_MASTER** snapshot you created previously.

Target Virtual Machine:

- a. For *Type*, verify that **Linked** is selected.
- b. For *Role*, verify that the **Normal** role is selected.
- c. For *Take Snapshot*, verify that **GOLDEN_MASTER** is inputted.
- d. For *Copy BIOS UUID*, only choose this option if you wish to preserve the sources VM's BIOS UUID for the targeted clone VM (when this option is checked, it can help with keeping licensing intact such as *Microsoft Windows Licensing/Activation*).



The screenshot displays the Proxmox VE VM settings interface. At the top, there are tabs for 'Client', 'Server1', 'Server2', 'Server3', and 'NAS'. Below these, the interface is divided into two main sections: 'Source Virtual Machine' (highlighted in green) and 'Target Virtual Machine' (highlighted in red). An arrow points from the Source to the Target section.


Source Virtual Machine settings:

- VM Name: PVE8_AAO_Master.Client
- From Snapshot: GOLDEN_MASTER (highlighted with a red box)

Target Virtual Machine settings:


- VM Name: PVE8_AAO_H120_S1001.Client
- Type: Linked (highlighted with a red box)
- Role: Normal (highlighted with a red box)
- Runtime Host: [Dropdown menu]
- Datastore: [Dropdown menu]
- Storage: On Demand
- Take Snapshot: GOLDEN_MASTER (highlighted with a red box)
- Copy BIOS UUID: ☐ disabled

9. When you are done changing settings, click **Clone Pod**. This should complete within a minute as we are creating linked virtual machines.



10. When the pod clone process is finished, click **OK**.

11. If you want to dedicate this pod to a particular class, team, or student, use the *Pod ACLs* feature. For details, see the [NETLAB+ VE Instructor Guide](#).
12. Click the **Online** Button on the *Pod Management* page to make the pod available.



The user pod can now be reserved. When the reservation becomes active, *NETLAB+* will automatically configure virtual machines and virtual networking for your new pod.



The *GOLDEN_MASTER* snapshot is the starting point for all pods. We recommend that you reserve the 1st pod and conduct some labs to make sure the snapshot images work correctly. If there are defects, make corrections to the images to the master pod and retake the *GOLDEN_MASTER* snapshot before creating additional pods.

5.3 Copying Your Master Pod to the Second Host

For this task, we will use the pod cloning utility to copy our master pod to the second host.

1. Log in to *NETLAB+* with the administrator account.
2. Select the **Pods** icon.



3. Click on the master pod.
4. Make sure the pod is offline by selecting **Take Pod Offline**.
5. Click the **Clone** button to create a new pod, based on the settings of this pod.



6. Input a new ID value into the **New Pod ID** field. It is advised to keep the pods in numerical order. If the pod IDs are not in numerical order, they will not show up in the scheduler in numerical order. Click **Next**.

7. Enter a name for the cloned pod into the **New Pod Name** field. For example, **PVE8_AAO_H130_M1000**. Click **Next**.



The **Pod Name** identifies the pod and is unique per pod. Here we used the name of the lab set or course in a shortened form along with a host identifier (H130), the type and number of the pod (M1000).


8. When the action has finished processing, you are presented with a settings screen. Notice each VM has its own tab. Go through each tab and verify the following:

Source Virtual Machine:

- a. *From Snapshot* should be set to the **GOLDEN_MASTER** snapshot you created previously.


Target Virtual Machine:

- a. For *Type*, verify that **Full** is selected.
- b. For *Role*, verify that the **Master** role is selected.
- c. For *Take Snapshot*, verify that **GOLDEN_MASTER** is inputted.
- d. For *Runtime Host*, select the second host system (which should be different than the system you are cloning from).
- e. For *Copy BIOS UUID*, only choose this option if you wish to preserve the sources VM's BIOS UUID for the targeted clone VM (when this option is checked, it can help with keeping licensing intact such as *Microsoft Windows Licensing/Activation*).



Source Virtual Machine		Target Virtual Machine	
VM Name	PVE8_AAO_Master.Client	VM Name	PVE8_AAO_H130_M1000.Client
From Snapshot	GOLDEN_MASTER	Type	Full
		Role	Master
		Runtime Host	[Host System]
		Datastore	[Datastore]
		Storage	On Demand
		Take Snapshot	GOLDEN_MASTER
		Copy BIOS UUID	<input type="checkbox"/> disabled

9. When you are done changing settings, click **Clone Pod**. This may take up to 30 minutes as full copies are being made. You may navigate away from the cloning progress screen, and then later return to the pod to check progress.



10. When the pod clone process is finished, click **OK**.
11. It is likely that you will need to reactivate the licensing on any Windows VMs in the Master pod on the second (third, etc.) host. Please test the master pod prior to cloning student pods.

5.4 Creating User Pods on the Second Host

To create user pods on the second host, repeat the steps to create user pods on the first host (see [Creating User Pods](#)), substituting the second master pod (created in the previous section) as the cloning source.

5.5 Assigning Pods to Students, Teams, or Classes

Please refer to the [NETLAB+ VE Instructor Guide](#) for details on using the *Pod ACLs* feature.